



# LHC COMPUTING GRID

## LCG - TAR\_UI - GENERIC CONFIGURATION REFERENCE

---

<i>Document identifier:</i>	<b>LCG-GIS-CR-TAR_UI</b>
<i>EDMS id:</i>	<b>none</b>
<i>Version:</i>	
<i>Date:</i>	<b>January 16, 2006</b>
<i>Section:</i>	<b>LCG Grid Infrastructure Support</b>
<i>Document status:</i>	<b>ACTIVE</b>
<i>Author(s):</i>	Keeble, Oliver;LCG Deployment - GIS team;Retico, Antonio;Vidic, Valentin;
<i>File:</i>	<b>TAR_UI</b>

---

*Abstract: Configuration steps done by the YAIM script 'configure\_TAR\_UI'*

---



---

## CONTENTS

<b>1. INTRODUCTION.....</b>	<b>4</b>
<b>2. VARIABLES.....</b>	<b>5</b>
<b>3. SET TAR UI DEFAULTS .....</b>	<b>7</b>
3.1. SPECIFICATION OF FUNCTION: CONFIG_TAR_UI_DEFAULTS .....	7
<b>4. CHECK TAR INSTALLATION.....</b>	<b>8</b>
4.1. SPECIFICATION OF FUNCTION: CONFIG_CHECK_TAR.....	8
<b>5. INSTALL CA CERTIFICATES .....</b>	<b>9</b>
5.1. SPECIFICATION OF FUNCTION: INSTALL_CERTS_USERLAND.....	9
<b>6. FIX CRL UPDATE SCRIPT .....</b>	<b>10</b>
6.1. SPECIFICATION OF FUNCTION: CONFIG_FIX_EDG-FETCH-CRL-CRON.....	10
<b>7. SET-UP UPDATING OF CRLS.....</b>	<b>11</b>
7.1. SPECIFICATION OF FUNCTION: CONFIG_CRL .....	11
<b>8. SET-UP REPLICA MANAGER.....</b>	<b>12</b>
8.1. SPECIFICATION OF FUNCTION: CONFIG_REPLICA_MANAGER .....	12
<b>9. SET-UP USER ENVIRONMENT .....</b>	<b>13</b>
9.1. SPECIFICATION OF FUNCTION: CONFIG_TAR_USER_ENV .....	13
<b>10. SET-UP LCG ENVIRONMENT VARIABLES.....</b>	<b>14</b>
10.1. SPECIFICATION OF FUNCTION: CONFIG_LCGENV .....	16
<b>11. SET-UP JAVA LOCATION.....</b>	<b>17</b>
11.1. SPECIFICATION OF FUNCTION: CONFIG_JAVA.....	17
<b>12. SET-UP R-GMA CLIENT .....</b>	<b>18</b>
12.1. SPECIFICATION OF FUNCTION: CONFIG_RGMA_CLIENT .....	18
<b>13. SET-UP WORKLOAD MANAGER CLIENT.....</b>	<b>19</b>
13.1. SPECIFICATION OF FUNCTION: CONFIG_WORKLOAD_MANAGER_CLIENT.....	20
<b>14. CONFIGURE THE VOMSES FILES .....</b>	<b>21</b>
14.1. SPECIFICATION OF FUNCTION: CONFIG_VOMSES .....	21
<b>15. SET-UP FILE TRANSFER SERVICE CLIENT.....</b>	<b>22</b>
15.1. SPECIFICATION OF FUNCTION: CONFIG_FTS_CLIENT .....	22



---

<b>16. SOURCE CODE</b> .....	<b>23</b>
16.1. CONFIG_TAR_UI_DEFAULTS .....	23
16.2. CONFIG_CHECK_TAR .....	23
16.3. INSTALL_CERTS_USERLAND .....	24
16.4. CONFIG_FIX_EDG-FETCH-CRL-CRON .....	25
16.5. CONFIG_CRL .....	25
16.6. CONFIG_REPLICA_MANAGER .....	26
16.7. CONFIG_TAR_USER_ENV .....	27
16.8. CONFIG_LCGENV .....	30
16.9. CONFIG_JAVA .....	34
16.10. CONFIG_RGMA_CLIENT .....	36
16.11. CONFIG_WORKLOAD_MANAGER_CLIENT .....	37
16.12. CONFIG_VOMSES .....	39
16.13. CONFIG_FTS_CLIENT .....	40



## 1. INTRODUCTION

This document lists the manual steps for the installation and configuration of a LCG TAR\_UI Node. Furthermore it provides a specification of the YAIM functions used to configure the node with the script-based configuration.

The configuration has been tested on a standard Scientific Linux 3.0 Installation.

Link to this document:

This document is available on the *Grid Deployment* web site

<http://www.cern.ch/grid-deployment/gis/lcg-GCR/index.html>



## 2. VARIABLES

In order to set-up a TAR\_UI node, you need at least the following variables to be correctly configured in the site configuration file (site-info.def):

**BDII\_HOST** : BDII Hostname.

**CE\_HOST** : Computing Element Hostname.

**DPM\_HOST** : Host name of the DPM host, used also as a default DPM for the lcg-stdout-mon .

**EDG\_WL\_SCRATCH** : Optional scratch directory for jobs.

**EDG\_WL\_SCRATCH** : Optional scratch directory for jobs.

**FTS\_SERVER\_URL** : URL of the File Transfer Service server.

**GLOBUS\_TCP\_PORT\_RANGE** : Port range for Globus IO.

**GSSKLOG** : yes or no, indicating whether the site provides an AFS authentication server which maps gsi credentials into Kerberos tokens .

**GSSKLOG\_SERVER** : If GSSKLOG is yes, the name of the AFS authentication server host.

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**JAVA\_LOCATION** : Path to Java VM installation. It can be used in order to run a different version of java installed locally.

**MON\_HOST** : MON Box Hostname.

**OUTPUT\_STORAGE** : Default Output directory for the jobs.

**PX\_HOST** : PX hostname.

**RB\_HOST** : Resource Broker Hostname.

**REG\_HOST** : RGMA Registry hostname.

**SE\_LIST** : A list of hostnames of the SEs available at your site.

**SITE\_NAME** : Your GIIS.

**VOBOX\_HOST** : VOBOX hostname.

**VOS** : List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:

**VO\_<VO-NAME>\_SE** : Default SE used by the VO. WARNING: VO-NAME must be in capital cases.



---

**VO\_<VO-NAME>\_SW\_DIR** : Area on the WN for the installation of the experiment software.

If on the WNs a predefined shared area has been mounted where VO managers can pre-install software, then these variable should point to this area. If instead there is not a shared area and each job must install the software, then this variables should contain a dot ( . ).Anyway the mounting of shared areas, as well as the local installation of VO software is not managed by *yaim* and should be handled locally by Site Administrators. **WARNING:** VO-NAME must be in capital cases.

**VO\_<VO-NAME>\_VOMSES** : List of entries for the vomses files for this VO. Multiple values can be given if enclosed in single quotes.



### 3. SET TAR UI DEFAULTS

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_tar\_ui\_defaults*'.

Defaults for various services are set (if not already defined in *site-info.def*):

```
RB_HOST=lxn1177.cern.ch
PX_HOST=my-proxy.cern.ch
BDII_HOST=lcg-bdii.cern.ch
MON_HOST=norgma
REG_HOST=norgma
VOS="atlas alice lhcb cms dteam sixt na48"
```

#### 3.1. SPECIFICATION OF FUNCTION: CONFIG\_TAR\_UI\_DEFAULTS

The function '*config\_tar\_ui\_defaults*' needs the following variables to be set in the configuration file:

**BDII\_HOST** : BDII Hostname.

**MON\_HOST** : MON Box Hostname.

**PX\_HOST** : PX hostname.

**RB\_HOST** : Resource Broker Hostname.

**REG\_HOST** : RGMA Registry hostname.

**VOS** : List of supported VOs.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_tar_ui_defaults
```

The code is also reproduced in 16.1..



## 4. CHECK TAR INSTALLATION

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_check\_tar*'.

Check if `<INSTALL_ROOT>` directory exists.

Check if dependency software is installed (test if `<INSTALL_ROOT>/edg/share/java/log4j.jar` exists).

### 4.1. SPECIFICATION OF FUNCTION: CONFIG\_CHECK\_TAR

The function '*config\_check\_tar*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_check_tar`

The code is also reproduced in 16.2..



## 5. INSTALL CA CERTIFICATES

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function *'install\_certs\_userland'*.

If CA certificates are not already installed in */etc/grid-security/certificates*, certificate RPMs are downloaded from <http://grid-deployment.web.cern.ch/grid-deployment/download/RpmDir/security/index.html> and extracted to *<INSTALL\_ROOT>/etc/grid-security/certificates*.

### 5.1. SPECIFICATION OF FUNCTION: INSTALL\_CERTS\_USERLAND

The function *'install\_certs\_userland'* needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/install_certs_userland`

The code is also reproduced in 16.3..



---

## 6. FIX CRL UPDATE SCRIPT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_fix\_edg-fetch-crl-cron*'.

CRL update script (*<INSTALL\_ROOT>/edg/etc/cron/edg-fetch-crl-cron*) is modified to use *<INSTALL\_ROOT>/edg* as *EDG\_LOCATION* and *<INSTALL\_ROOT>/etc/grid-security/certificates* as *X509\_CERT\_DIR*.

### 6.1. SPECIFICATION OF FUNCTION: CONFIG\_FIX\_EDG-FETCH-CRL-CRON

The function '*config\_fix\_edg-fetch-crl-cron*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_fix_edg-fetch-crl-cron`

The code is also reproduced in 16.4..



---

## 7. SET-UP UPDATING OF CRLS

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_crl*'.

Cron script is installed to fetch new versions of CRLs four times a day. The time when the script is run is randomized in order to distribute the load on CRL servers. If the configuration is run as root, the cron entry is installed in */etc/cron.d/edg-fetch-crl*, otherwise it is installed as a user cron entry.

CRLs are also updated immediately by running the update script (*<INSTALL\_ROOT>/edg/etc/cron/edg-fetch-crl-cron*).

Logrotate script is installed as */etc/logrotate.d/edg-fetch-crl* to prevent the logs from growing indefinitely.

### 7.1. SPECIFICATION OF FUNCTION: CONFIG\_CRL

The function '*config\_crl*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_crl`

The code is reproduced also in 16.5..



## 8. SET-UP REPLICA MANAGER

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function *'config\_replica\_manager'*.

Variable substitutions are generated in `<INSTALL_ROOT>/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local`:

```
@EDG.LOCATION@|<INSTALL_ROOT>/edg|location of edg middleware
@LOCALDOMAIN@|<domain>|the local domain
@DEFAULT.SE@|<SE_HOST>|the host of the close SE
@DEFAULT.CE@|<CE_HOST>|the host of the close CE
@INFOSERVICE@|MDS|The info provider to use. It can be Stub, MDS or RGMA
@RLS.MODE@|LrcOnly|The mode the RLS should be run in. LrcOnly or WithRli
@STUBFILE@||The properties file for the static file - only needed in Stub mode
@MDS.HOST@|<BDII_HOST>|The host of the MDS info provider
@MDS.PORT@|2170|The port of the MDS info provider
@ROS.FAILURE@|false|Fail if no ROS is available
@CONF.GCC@|_gcc3_2_2|The gcc suffix as used on the build box (empty for 2.95, _gcc3_2_2 for 3.2.)
@IGNORE.PREFIX@|true|Whether the RM will ignore the lfn and guid prefix.
@GRIDFTP.DCAU@|false|Does GridFTP use Data Channel Authentication (DCAU)
@GRIDFTP.STREAMS.SMALL@|1|The default number of stream to use for a small file
@GRIDFTP.STREAMS.BIG@|3|The default number of stream to use for a big file
@GRIDFTP.FILESIZESIZE.THRESHOLD@|100|The Threshold (in MB) above which a file to transfer is considered "big"
```

The value of `<domain>` is determined by running *hostname -d*. Using these substitutions and templates in `<INSTALL_ROOT>/edg/etc/edg-replica-manager/`, Replica Manager is configured by generating files in `<EDG_LOCATION>/var/etc/edg-replica-manager`:

```
<INSTALL_ROOT>/edg/sbin/edg-replica-manager-configure <INSTALL_ROOT>/edg/etc/edg-replica-manager/edg-replica-manage
```

### 8.1. SPECIFICATION OF FUNCTION: CONFIG\_REPLICA\_MANAGER

The function *'config\_replica\_manager'* needs the following variables to be set in the configuration file:

**BDII\_HOST** : BDII Hostname.

**CE\_HOST** : Computing Element Hostname.

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**SE\_LIST** : A list of hostnames of the SEs available at your site.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_replica_manager
```

The code is also reproduced in 16.6..



## 9. SET-UP USER ENVIRONMENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_tar\_user\_env*'.

<*INSTALL\_ROOT*>/etc/profile.d/grid\_env.sh and <*INSTALL\_ROOT*>/etc/profile.d/grid\_env.csh are fixed to use the correct location of LCG software:

```
UI_LOC=<INSTALL_ROOT>
```

If CA certificates are installed in <*INSTALL\_ROOT*>/etc/grid-security/certificates, *X509\_CERT\_DIR* is also modified appropriately.

### 9.1. SPECIFICATION OF FUNCTION: CONFIG\_TAR\_USER\_ENV

The function '*config\_tar\_user\_env*' needs the following variables to be set in the configuration file:

**GLOBUS\_TCP\_PORT\_RANGE** : Port range for Globus IO.

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_tar_user_env
```

The code is also reproduced in 16.7..



## 10. SET-UP LCG ENVIRONMENT VARIABLES

Author(s): Retico, Antonio

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_lcgenv*'.

The LCG middleware needs some environment variables to be set up at boot time. The variable should be available both in 'bash-like' shells and in 'csh-like' shells.

This can be obtained in different ways:

The simplest way, if you have 'root' permissions, is to put a shell script for each of the supported shell 'families' in the directory */etc/profile.d*. The script will be automatically sourced at start up.

If instead you are not a superuser and you are doing the installation in a private directory (e.g. you are installing a Re-locatable Distribution of a Worker Node or a User Interface in the *<INSTALL\_ROOT>* directory), you could create the scripts in the directory *<INSTALL\_ROOT>/etc/profile.d*, in order to have the variables automatically set up by LCG tools.

The list of the environment variables to be set up follows:

**LCG\_GFAL\_INFOSYS:** Hostname of the BDII node.

**MYPROXY\_SERVER:** Hostname of the Proxy server.

**PATH:** Add to the PATH variable the path */opt/d-cache-client/bin*

**LD\_LIBRARY\_PATH:** Add to the LD\_LIBRARY\_PATH variable the path */opt/d-cache-client/dcap*

**SRM\_PATH:** Installation directory of the srm client. The default value for this variable is */opt/d-cache-client/srm*

**VO\_<VO-NAME>\_SW\_DIR:** For each virtual organization <VO-NAME> An environment variable VO\_<VO-NAME>\_SW\_DIR is needed. This variable points to the installation directory of the VO software.

**VO\_<VO-NAME>\_DEFAULT\_SE:** For each virtual organization <VO-NAME> An environment variable VO\_<VO-NAME>\_DEFAULT\_SE is needed. This variable points to the Default Storage Element for that VO.

The examples given hereafter refer to the simple configuration method described above. In the following description we will refer to the two possible locations as to the *<LCG\_ENV\_LOC>*. So, according to the cases above described, either

*<LCG\_ENV\_LOC>=/etc/profile.d*



or

`<LCG_ENV_LOC>=<INSTALL_ROOT>/etc/profile.d`

Examples:

- Example of file `<LCG_ENV_LOC>/lcgen.sh`:

```
#!/bin/sh
export LCG_GFAL_INFOSYS=lx1769.cern.ch:2170
export MYPROXY_SERVER=lx1774.cern.ch
export PATH="${PATH}:/opt/d-cache-client/bin"
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:/opt/d-cache-client/dcap
export SRM_PATH=/opt/d-cache-client/srm
export VO_ATLAS_SW_DIR=lx1780.cern.ch
export VO_ATLAS_DEFAULT_SE=lx1780.cern.ch
export VO_ALICE_SW_DIR=lx1780.cern.ch
export VO_ALICE_DEFAULT_SE=lx1780.cern.ch
export VO_LHCB_SW_DIR=lx1780.cern.ch
export VO_LHCB_DEFAULT_SE=lx1780.cern.ch
export VO_CMS_SW_DIR=lx1780.cern.ch
export VO_CMS_DEFAULT_SE=lx1780.cern.ch
export VO_DTEAM_SW_DIR=lx1780.cern.ch
export VO_DTEAM_DEFAULT_SE=lx1780.cern.ch
```

- Example of file `<LCG_ENV_LOC>/lcgen.csh`:

```
#!/bin/csh
setenv LCG_GFAL_INFOSYS lx1769.cern.ch:2170
setenv MYPROXY_SERVER lx1774.cern.ch
setenv PATH "${PATH}:/opt/d-cache-client/bin"
setenv LD_LIBRARY_PATH ${LD_LIBRARY_PATH}:/opt/d-cache-client/dcap
setenv SRM_PATH /opt/d-cache-client/srm
setenv VO_ATLAS_SW_DIR lx1780.cern.ch
setenv VO_ATLAS_DEFAULT_SE lx1780.cern.ch
setenv VO_ALICE_SW_DIR lx1780.cern.ch
setenv VO_ALICE_DEFAULT_SE lx1780.cern.ch
setenv VO_LHCB_SW_DIR lx1780.cern.ch
setenv VO_LHCB_DEFAULT_SE lx1780.cern.ch
setenv VO_CMS_SW_DIR lx1780.cern.ch
setenv VO_CMS_DEFAULT_SE lx1780.cern.ch
setenv VO_DTEAM_SW_DIR lx1780.cern.ch
setenv VO_DTEAM_DEFAULT_SE lx1780.cern.ch
```

**WARNING:** The two scripts must be executable by all users.

```
> chmod a+x ${LCG_ENV_LOC}/lcgen.csh
> chmod a+x ${LCG_ENV_LOC}/lcgen.sh
```



## 10.1. SPECIFICATION OF FUNCTION: CONFIG\_LCGENV

The function '*config\_lcgen*' needs the following variables to be set in the configuration file:

**BDII\_HOST** : BDII Hostname.

**CE\_HOST** : Computing Element Hostname.

**DPM\_HOST** : Host name of the DPM host, used also as a default DPM for the *lcg-stdout-mon* .

**EDG\_WL\_SCRATCH** : Set this if you want jobs to use a particular scratch area.

**EDG\_WL\_SCRATCH** : Set this if you want jobs to use a particular scratch area.

**GLOBUS\_TCP\_PORT\_RANGE** : Port range for Globus IO.

**GSSKLOG** : yes or no, indicating whether the site provides an AFS authentication server which maps gsi credentials into Kerberos tokens .

**GSSKLOG\_SERVER** : If GSSKLOG is yes, the name of the AFS authentication server host.

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**PX\_HOST** : PX hostname.

**SE\_LIST** : A list of hostnames of the SEs available at your site.

**SITE\_NAME** : Your GIIS.

**VOBOX\_HOST** : VOBOX hostname.

**VOS** : List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:

**VO\_<VO-NAME>\_SE** : Default SE used by the VO. WARNING: VO-NAME must be in capital cases.

**VO\_<VO-NAME>\_SW\_DIR** : Area on the WN for the installation of the experiment software. If on the WNs a predefined shared area has been mounted where VO managers can pre-install software, then these variable should point to this area. If instead there is not a shared area and each job must install the software, then this variables should contain a dot ( . ). Anyway the mounting of shared areas, as well as the local installation of VO software is not managed by *yaim* and should be handled locally by Site Administrators. WARNING: VO-NAME must be in capital cases.

The function does exit with return code 1 if they are not set.

The original code of the function can be found in:

`/opt/lcg/yaim/functions/config_lcgen`

The code is reproduced also in 16.8..



## 11. SET-UP JAVA LOCATION

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_java*'.

Since Java is not included in the LCG distribution, Java location needs to be configured with *yaim*.

If `<JAVA_LOCATION>` is not defined in *site-info.def*, it is determined from installed Java RPMs (if available).

In relocatable distribution, `JAVA_HOME` environment variable is defined in `<INSTALL_ROOT>/etc/profile.d/grid_en` and `<INSTALL_ROOT>/etc/profile.d/grid_env.csh`.

Otherwise, `JAVA_HOME` is defined in `/etc/java/java.conf` and `/etc/java.conf` and Java binaries added to `PATH` in `<INSTALL_ROOT>/edg/etc/profile.d/j2.sh` and `<INSTALL_ROOT>/edg/etc/profile.d/j2.csh`.

### 11.1. SPECIFICATION OF FUNCTION: CONFIG\_JAVA

The function '*config\_java*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**JAVA\_LOCATION** : Path to Java VM installation. It can be used in order to run a different version of java installed locally.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_java
```

The code is reproduced also in 16.9..



## 12. SET-UP R-GMA CLIENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_rgma\_client*'.

R-GMA client configuration is generated in `<INSTALL_ROOT>/glite/etc/rgma/rgma.conf` by running:

```
<INSTALL_ROOT>/glite/share/rgma/scripts/rgma-setup.py --secure=no --server=<MON_HOST> --registry=<REG_HOST> --scheme=<SCHEME>
```

`<INSTALL_ROOT>/edg/etc/profile.d/edg-rgma-env.sh` and `<INSTALL_ROOT>/edg/etc/profile.d/edg-rgma-env.csh` with the following functionality:

- `RGME_HOME` is set to `<INSTALL_ROOT>/glite`
- `APEL_HOME` is set to `<INSTALL_ROOT>/glite`
- `<INSTALL_ROOT>/glite/lib/python` is added to `PYTHONPATH`
- `<INSTALL_ROOT>/glite/lib` is added to `LD_LIBRARY_PATH`.

These files are sourced into the users environment from `<INSTALL_ROOT>/etc/profile.d/z_edg_profile.sh` and `<INSTALL_ROOT>/etc/profile.d/z_edg_profile.csh`.

### 12.1. SPECIFICATION OF FUNCTION: CONFIG\_RGMA\_CLIENT

The function '*config\_rgma\_client*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**MON\_HOST** : MON Box Hostname.

**REG\_HOST** : RGMA Registry hostname.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_rgma_client
```

The code is also reproduced in 16.10..



## 13. SET-UP WORKLOAD MANAGER CLIENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_workload\_manager\_client*'.

For each of the supported VOs, a configuration file is generated in `<INSTALL_ROOT>/edg/etc/<vo>/edg_wl_ui.conf`:

```
[
VirtualOrganisation = "<vo>";
NSAddresses = "<RB_HOST>:7772";
LBAddresses = "<RB_HOST>:9000";
## HLR location is optional. Uncomment and fill correctly for
## enabling accounting
#HLRLocation = "fake HLR Location"
## MyProxyServer is optional. Uncomment and fill correctly for
## enabling proxy renewal. This field should be set equal to
## MYPROXY_SERVER environment variable
MyProxyServer = "<PX_HOST>"
]
```

This file defines RB and MyProxy server to be used for a specific VO.

Defaults common to all VOs are defined in `<INSTALL_ROOT>/edg/etc/edg_wl_ui_cmd_var.conf`:

```
[
rank = - other.GlueCEStateEstimatedResponseTime;
requirements = other.GlueCEStateStatus == "Production";
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "<OUTPUT_STORAGE>";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "<RB_HOST>:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
```

and `<INSTALL_ROOT>/edg/etc/edg_wl_ui_gui_var.conf`:

```
[
JDLEDefaultSchema = "Glue";
Glue = [
rank = - other.GlueCEStateEstimatedResponseTime;
rankMPI = other.GlueCEStateFreeCPUs;
requirements = other.GlueCEStateStatus == "Production"
]
```



```
];
EDG = [
rank = - other.EstimatedTraversalTime;
rankMPI = other.FreeCPUs;
requirements = true
];
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "<OUTPUT_STORAGE>";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "<RB_HOST>:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
```

Directory for storing job output sandboxes (<OUTPUT\_STORAGE>) is created.

Finally, *edg-wl-ui-env.csh*, *edg-wl-ui-env.sh*, *edg-wl-ui-gui-env.csh* and *edg-wl-ui-gui-env.sh* are copied from <INSTALL\_ROOT>/edg/etc/profile.d/ to <INSTALL\_ROOT>/edg/var/etc/profile.d. These scripts are sourced from /etc/profile.d and are used to setup the environment for EDG programs.

### 13.1. SPECIFICATION OF FUNCTION: CONFIG\_WORKLOAD\_MANAGER\_CLIENT

The function '*config\_workload\_manager\_client*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**OUTPUT\_STORAGE** : Default Output directory for the jobs.

**PX\_HOST** : PX hostname.

**RB\_HOST** : Resource Broker Hostname.

**VOS** : List of supported VOs.

The original code of the function can be found in:

/opt/lcg/yaim/functions/config\_workload\_manager\_client

The code is also reproduced in 16.11..



---

## 14. CONFIGURE THE VOMSES FILES

Author(s): Keeble, Oliver

Email : support-lcg-manual-install@cern.ch

This chapter describes the configuration steps done by the *yaim* function '*config\_vomses*'.

This function creates the vomses configuration files. Each file contains one line of information describing a VOMS server. This information is used by commands like *voms-proxy-init* in order to create a voms proxy. The necessary information is taken from parameters in *site-info.def* (*VO<sub>X</sub>XX<sub>V</sub>OMSES*).

The files are placed in central directories if run as root, or in *.edg/vomses* if run as a user.

### 14.1. SPECIFICATION OF FUNCTION: CONFIG\_VOMSES

The function '*config\_vomses*' needs the following variables to be set in the configuration file:

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

**VOS** : List of supported VOs. For each item listed in the VOS variable you need to create a set of new variables as follows:

**VO\_<VO-NAME>\_VOMSES** : List of entries for the vomses files for this VO. Multiple values can be given if enclosed in single quotes.

The original code of the function can be found in:

```
/opt/lcg/yaim/functions/config_vomses
```

The code is also reproduced in 16.12..



## 15. SET-UP FILE TRANSFER SERVICE CLIENT

Author(s): Vidic, Valentin

Email : support-lcg-manual-install@cern.ch

*This chapter describes the configuration steps done by the yaim function 'config\_fts\_client'.*

*If <FTS\_SERVER\_URL> is set, gLite FTS client is configured by creating <INSTALL\_ROOT>/glite/etc/services.xml.*

```
<services>

<service name="EGEEfts">
  <parameters>
    <endpoint><FTS_SERVER_URL>/services/FileTransfer</endpoint>
    <type>org.glite.FileTransfer</type>
    <version>3.0.0</version>
  </parameters>
</service>

<service name="EGEEchannel">
  <parameters>
    <endpoint><FTS_SERVER_URL>/services/ChannelManagement</endpoint>
    <type>org.glite.ChannelManagement</type>
    <version>3.0.0</version>
  </parameters>
</service>

</services>
```

### 15.1. SPECIFICATION OF FUNCTION: CONFIG\_FTS\_CLIENT

*The function 'config\_fts\_client' needs the following variables to be set in the configuration file:*

**FTS\_SERVER\_URL** : URL of the File Transfer Service server.

**INSTALL\_ROOT** : Installation root - change if using the re-locatable distribution.

*The original code of the function can be found in:*

/opt/lcg/yaim/functions/config\_fts\_client

*The code is also reproduced in 16.13..*



## 16. SOURCE CODE

### 16.1. CONFIG\_TAR\_UI\_DEFAULTS

```
function config_tar_ui_defaults () {

if [ -z "$RB_HOST" ]; then
    RB_HOST=gdrb01.cern.ch
    PX_HOST=my-proxy.cern.ch
fi

if [ -z "$BDII_HOST" ]; then
    BDII_HOST=lcg-bdii.cern.ch
fi

if [ -z "$MON_HOST" ]; then
    MON_HOST="norgma"
    REG_HOST="norgma"
fi

if [ -z "$VOS" ]; then
    VOS="atlas alice lhcb cms dteam sixt na48"
fi

return 0

}
```

### 16.2. CONFIG\_CHECK\_TAR

```
function config_check_tar () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if [ ! -d ${INSTALL_ROOT} ]; then
    echo "please make the distribution available under ${INSTALL_ROOT}"
    echo "or update your site-info.def file to reflect the correct path"
    return 1
fi

if [ $SUID -ne 0 ]; then
    if [ ! -f ${INSTALL_ROOT}/edg/share/java/log4j.jar ]; then
        echo "You are attempting a userland installation"
        echo "Have you untarred the dependency software into"
        echo "${INSTALL_ROOT}/edg yet?"
        return 1
    fi
fi

return 0

}
```



```
}
```

### 16.3. INSTALL\_CERTS\_USERLAND

```
function install_certs_userland () {

if central_certs; then
    echo "Certificates found in /etc/grid-security/certificates"
    echo "Not installing relocated versions"
    return 0
fi

CA_WGET="http://grid-deployment.web.cern.ch/grid-deployment/download/RpmDir/security/index.html"

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if ! ( which rpm2cpio > /dev/null 2>&1 ); then
echo "rpm2cpio is required to install the CA rpms"
return 1
fi

mkdir tmp.$$ || return 1

cd tmp.$$

wget -ll -nd -r --quiet $CA_WGET

if ! (ls *.rpm > /dev/null 2>&1); then
echo "Couldn't download the CA rpms"
return 1
fi

for i in *.rpm; do
rpm2cpio $i | cpio -i --make-directories --quiet
done

if [ ! -d ${INSTALL_ROOT}/etc/grid-security/certificates ]; then
mkdir -p ${INSTALL_ROOT}/etc/grid-security/certificates
fi

mv -f etc/grid-security/certificates/* ${INSTALL_ROOT}/etc/grid-security/certificates

cd - > /dev/null

rm -rf tmp.$$

return 0

}
```



## 16.4. CONFIG\_FIX\_EDG-FETCH-CRL-CRON

```
function config_fix_edg-fetch-crl-cron () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

ex $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron <<EOF
%s#^\$para{EDG_LOCATION}=". *";#\$para{EDG_LOCATION}="$INSTALL_ROOT/edg";#
w
q
EOF

ex $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron <<EOF
%s#^\$para{X509_CERT_DIR}=". *";#\$para{X509_CERT_DIR}="$INSTALL_ROOT/etc/grid-security/certificates";#
w
q
EOF

return 0

}
```

## 16.5. CONFIG\_CRL

```
config_crl(){

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

let minute="$RANDOM%60"

let h1="$RANDOM%24"
let h2="($h1+6)%24"
let h3="($h1+12)%24"
let h4="($h1+18)%24"

if !( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then

    if [ ! -f /etc/cron.d/edg-fetch-crl ]; then
echo "Now updating the CRLs - this may take a few minutes..."
$INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> /var/log/edg-fetch-crl-cron.log 2>&1
fi

cron_job edg-fetch-crl root "$minute $h1,$h2,$h3,$h4 * * * $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> /var/lo

cat <<EOF > /etc/logrotate.d/edg-fetch
/var/log/edg-fetch-crl-cron.log {
    compress
    monthly
    rotate 12
    missingok
    ifempty
    create
}
}
```



EOF

else

```
    cron_job edg-fetch-crl `whoami` "$minute $h1,$h2,$h3,$h4 * * * $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >>
    if [ ! -d $INSTALL_ROOT/edg/var/log ]; then
mkdir -p $INSTALL_ROOT/edg/var/log
    fi
    echo "Now updating the CRLs - this may take a few minutes..."
    $INSTALL_ROOT/edg/etc/cron/edg-fetch-crl-cron >> $INSTALL_ROOT/edg/var/log/edg-fetch-crl-cron.log 2>&1

fi

return 0
}
```

## 16.6. CONFIG\_REPLICA\_MANAGER

```
config_replica_manager(){

# SE_HOST and CE_HOST are not strictly required
requires BDII_HOST

se_host="${SE_LIST%% *}"

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if [ -f ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local ]; then
    mv -f ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local /tmp/edg-replica-ma
fi

cat <<EOF > ${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local
@EDG.LOCATION@|${INSTALL_ROOT}/edg|location of edg middleware
@LOCALDOMAIN@|`hostname -d`|the local domain
@DEFAULT.SE@|${se_host}|the host of the close SE
@DEFAULT.CE@|${CE_HOST}|the host of the close CE
@INFOSERVICE@|MDS|The info provider to use. It can be Stub, MDS or RGMA
@RLS.MODE@|LrcOnly|The mode the RLS should be run in. LrcOnly or WithRli
@STUBFILE@||The properties file for the static file - only needed in Stub mode
@MDS.HOST@|${BDII_HOST}|The host of the MDS info provider
@MDS.PORT@|2170|The port of the MDS info provider
@ROS.FAILURE@|false|Fail if no ROS is available
@CONF.GCC@|_gcc3_2_2|The gcc suffix as used on the build box (empty for 2.95, _gcc3_2_2 for 3.2.)
@IGNORE.PREFIX@|true|Whether the RM will ignore the lfn and guid prefix.
@GRIDFTP.DCAU@|false|Does GridFTP use Data Channel Authentication (DCAU)
@GRIDFTP.STREAMS.SMALL@|1|The default number of stream to use for a small file
@GRIDFTP.STREAMS.BIG@|3|The default number of stream to use for a big file
@GRIDFTP.FILESIZETHRESHOLD@|100|The Threshold (in MB) above which a file to transfer is considered "big"
EOF

oldEDG_LOCATION=${EDG_LOCATION}
oldEDG_LOCATION_VAR=${EDG_LOCATION_VAR}
```



```
export EDG_LOCATION=${INSTALL_ROOT}/edg
export EDG_LOCATION_VAR=${INSTALL_ROOT}/edg/var

${INSTALL_ROOT}/edg/sbin/edg-replica-manager-configure \
${INSTALL_ROOT}/edg/etc/edg-replica-manager/edg-replica-manager.conf.values_local >> $YAIM_LOG

export EDG_LOCATION=${oldEDG_LOCATION}
export EDG_LOCATION_VAR=${oldEDG_LOCATION_VAR}

return 0
}
```

## 16.7. CONFIG\_TAR\_USER\_ENV

```
function config_tar_user_env () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if ( ! central_certs ); then
    x509_cert_dir=${INSTALL_ROOT}/etc/grid-security/certificates
else
    x509_cert_dir=${X509_CERT_DIR:-/etc/grid-security/certificates}
fi

if [ ! -d /etc/grid-security/vomsdir -a -d $INSTALL_ROOT/etc/grid-security/vomsdir ]; then
    x509_voms_dir=${INSTALL_ROOT}/etc/grid-security/vomsdir
else
    x509_voms_dir=${X509_VOMS_DIR:-/etc/grid-security/vomsdir}
fi

# If GLOBUS_TCP_PORT_RANGE is unset, give it a good default
GLOBUS_TCP_PORT_RANGE=${GLOBUS_TCP_PORT_RANGE:-"20000 25000"}

#####
# sh
#####

cat > $INSTALL_ROOT/etc/profile.d/grid_env.sh <<EOF

# Edit this line to reflect the mountpoint of your middleware
INSTALL_ROOT="$INSTALL_ROOT"
EOF

cat >> $INSTALL_ROOT/etc/profile.d/grid_env.sh <<'EOF'

# Leave the rest...

if [ "${LCG_ENV_SET}" ]; then return 0; fi

# Root directory for EDG software. (mandatory)
# Usual value: /opt/edg
```



```
EDG_LOCATION=${INSTALL_ROOT}/edg
# Directory for machine-specific files.
# Usual value: $EDG_LOCATION/var
EDG_LOCATION_VAR=$EDG_LOCATION/var
# World writable directory for temporary files. (mandatory)
# Usual value: /tmp
EDG_TMP=/tmp
EDG_WL_LOCATION=$EDG_LOCATION

# Usual value: /opt/lcg
LCG_LOCATION=${INSTALL_ROOT}/lcg
# Directory for machine-specific files.
# Usual value: $LCG_LOCATION/var
LCG_LOCATION_VAR=$LCG_LOCATION/var
# World writable directory for temporary files. (mandatory)
# Usual value: /tmp
LCG_TMP=/tmp

GLOBUS_LOCATION=${INSTALL_ROOT}/globus
#GLOBUS_CONFIG=/etc/globus.conf
GLOBUS_CONFIG=/dev/null

GPT_LOCATION=${INSTALL_ROOT}/gpt

GLITE_LOCATION=${INSTALL_ROOT}/glite
GLITE_LOCATION_VAR=${GLITE_LOCATION}/var

for i in ${INSTALL_ROOT}/etc/env.d/*.sh; do
    if [ -x $i ]; then
        . $i
    fi
done

LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${INSTALL_ROOT}/edg/externals/lib

if [ -d ${INSTALL_ROOT}/gcc-3.2.2/lib ]; then
    LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${INSTALL_ROOT}/gcc-3.2.2/lib
fi

RGMA_HOME="${INSTALL_ROOT}/glite"

export EDG_LOCATION EDG_LOCATION_VAR EDG_TMP EDG_WL_LOCATION LCG_LOCATION LCG_LOCATION_VAR LCG_TMP JAVA_HOME GLOBUS

EOF

cat >> $INSTALL_ROOT/etc/profile.d/grid_env.sh <<EOF

GLOBUS_TCP_PORT_RANGE="${GLOBUS_TCP_PORT_RANGE}"
export GLOBUS_TCP_PORT_RANGE

X509_CERT_DIR=$x509_cert_dir
X509_VOMS_DIR=$x509_voms_dir
export X509_CERT_DIR X509_VOMS_DIR
```



EOF

```
#####  
# csh  
#####
```

```
cat > $INSTALL_ROOT/etc/profile.d/grid_env.csh <<EOF
```

```
# Edit this line to reflect the mountpoint of your middleware  
setenv INSTALL_ROOT "$INSTALL_ROOT"  
EOF
```

```
cat >> $INSTALL_ROOT/etc/profile.d/grid_env.csh <<'EOF'
```

```
# Leave the rest...
```

```
if ( $?LCG_ENV_SET ) then  
    return 0  
endif
```

```
# Root directory for EDG software. (mandatory)  
# Usual value: /opt/edg  
setenv EDG_LOCATION ${INSTALL_ROOT}/edg  
# Directory for machine-specific files.  
# Usual value: $EDG_LOCATION/var  
setenv EDG_LOCATION_VAR $EDG_LOCATION/var  
# World writable directory for temporary files. (mandatory)  
# Usual value: /tmp  
setenv EDG_TMP /tmp  
setenv EDG_WL_LOCATION $EDG_LOCATION
```

```
# Usual value: /opt/lcg  
setenv LCG_LOCATION ${INSTALL_ROOT}/lcg  
# Directory for machine-specific files.  
# Usual value: $LCG_LOCATION/var  
setenv LCG_LOCATION_VAR $LCG_LOCATION/var  
# World writable directory for temporary files. (mandatory)  
# Usual value: /tmp  
setenv LCG_TMP /tmp
```

```
setenv GLOBUS_LOCATION ${INSTALL_ROOT}/globus  
#setenv GLOBUS_CONFIG /etc/globus.conf  
setenv GLOBUS_CONFIG /dev/null
```

```
setenv GPT_LOCATION ${INSTALL_ROOT}/gpt
```

```
setenv GLITE_LOCATION ${INSTALL_ROOT}/glite  
setenv GLITE_LOCATION_VAR ${GLITE_LOCATION}/var
```

```
foreach i (${INSTALL_ROOT}/etc/env.d/*.csh)  
    if ( -x $i ) then  
        source $i  
    endif
```



```
end

setenv LD_LIBRARY_PATH ${LD_LIBRARY_PATH}:${INSTALL_ROOT}/edg/externals/lib

if ( -d ${INSTALL_ROOT}/gcc-3.2.2/lib ) then
    setenv LD_LIBRARY_PATH ${LD_LIBRARY_PATH}:${INSTALL_ROOT}/gcc-3.2.2/lib
endif

setenv RGMA_HOME "${INSTALL_ROOT}/glite"

EOF

cat >>${INSTALL_ROOT}/etc/profile.d/grid_env.csh <<EOF
setenv GLOBUS_TCP_PORT_RANGE "$GLOBUS_TCP_PORT_RANGE"

setenv X509_CERT_DIR $x509_cert_dir
setenv X509_VOMS_DIR $x509_voms_dir
EOF

if [ $UID -eq 0 ]; then
echo "If you want this to be your default middleware installation"
echo "please run the following command"
echo "ln -s ${INSTALL_ROOT}/etc/profile.d/grid_env.sh ${INSTALL_ROOT}/etc/profile.d/grid_env.csh /etc/profile.d"
else
echo "IMPORTANT"
echo "you need to make sure that the correct grid_env.*sh file in"
echo "${INSTALL_ROOT}/etc/profile.d/"
echo "is sourced when you log in so that your"
echo "environment is set up correctly"
fi

}

}
```

## 16.8. CONFIG\_LCGENV

```
config_lcgenv() {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if !( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then
LCG_ENV_LOC=/etc/profile.d
else
LCG_ENV_LOC=${INSTALL_ROOT}/etc/env.d
fi

requires BDII_HOST SITE_NAME CE_HOST

if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
    requires VOS VO__SW_DIR SE_LIST
fi

}
```



```
default_se="${SE_LIST%% *}"

if [ "$default_se" ]; then
  for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do
    if [ "x`eval echo '$VO_${VO}_DEFAULT_SE`" = "x" ]; then
      eval VO_${VO}_DEFAULT_SE=$default_se
    fi
  done
fi

##### sh #####
cat << EOF > ${LCG_ENV_LOC}/lcgen.sh
#!/bin/sh
if test "x${LCG_ENV_SET+x}" = x; then
export LCG_GFAL_INFOSYS=$BDII_HOST:2170
EOF

if [ "$PX_HOST" ]; then
echo "export MYPROXY_SERVER=$PX_HOST" >> ${LCG_ENV_LOC}/lcgen.sh
fi

if ( echo "${NODE_TYPE_LIST}" | egrep -q 'WN|VOBOX' ); then
  if [ "$SITE_NAME" ]; then
echo "export SITE_NAME=$SITE_NAME" >> ${LCG_ENV_LOC}/lcgen.sh
  fi

  if [ "$CE_HOST" ]; then
echo "export SITE_GIIS_URL=$CE_HOST" >> ${LCG_ENV_LOC}/lcgen.sh
  fi
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm/bin ]; then
echo export PATH="\${PATH}:${INSTALL_ROOT}/d-cache/srm/bin:${INSTALL_ROOT}/d-cache/dcap/bin" >> ${LCG_ENV_LOC}/lcgen.sh
fi

if [ -d ${INSTALL_ROOT}/d-cache/dcap/lib ]; then
echo export LD_LIBRARY_PATH="\${LD_LIBRARY_PATH}:${INSTALL_ROOT}/d-cache/dcap/lib" >> ${LCG_ENV_LOC}/lcgen.sh
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm ]; then
echo export SRM_PATH=${INSTALL_ROOT}/d-cache/srm >> ${LCG_ENV_LOC}/lcgen.sh
fi

if [ "$EDG_WL_SCRATCH" ]; then
echo "export EDG_WL_SCRATCH=$EDG_WL_SCRATCH" >> ${LCG_ENV_LOC}/lcgen.sh
fi

for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do

  default_se=`eval echo '$VO_${VO}_DEFAULT_SE`
  if [ "$default_se" ]; then
echo "export VO_${VO}_DEFAULT_SE=$default_se" >> ${LCG_ENV_LOC}/lcgen.sh
  fi
done
```



```
    if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
sw_dir=`eval echo '$VO_${VO}_SW_DIR`
if [ "$sw_dir" ]; then
    echo "export VO_${VO}_SW_DIR=$sw_dir" >> ${LCG_ENV_LOC}/lcgenenv.sh
fi
fi

done

if [ "$VOBOX_HOST" ]; then
requires GSSKLOG
if [ "${GSSKLOG}x" == "yesx" ]; then
    requires GSSKLOG_SERVER
    echo "export GSSKLOG_SERVER=$GSSKLOG_SERVER" >> ${LCG_ENV_LOC}/lcgenenv.sh
fi
fi

if [ "${DPM_HOST}" ]; then
    echo "export DPNS_HOST=${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.sh
    echo "export DPM_HOST=${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.sh
fi

if [ "$GLOBUS_TCP_PORT_RANGE" ]; then
    echo "export MYPROXY_TCP_PORT_RANGE=\"${GLOBUS_TCP_PORT_RANGE}/ /,}\" >> ${LCG_ENV_LOC}/lcgenenv.sh
fi

if ( echo $NODE_TYPE_LIST | egrep -q UI ); then
    cat << EOF >> ${LCG_ENV_LOC}/lcgenenv.sh
if [ "x${X509_USER_PROXY}" = "x" ]; then
    export X509_USER_PROXY=/tmp/x509up_u${id -u}
fi
EOF
fi

echo fi >> ${LCG_ENV_LOC}/lcgenenv.sh
##### sh #####

##### csh #####
cat << EOF > ${LCG_ENV_LOC}/lcgenenv.csh
#!/bin/csh
if ( ! \${LCG_ENV_SET} ) then
setenv LCG_GFAL_INFOSYS $BDII_HOST:2170
EOF

if [ "$PX_HOST" ]; then
echo "setenv MYPROXY_SERVER $PX_HOST" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if ( echo "${NODE_TYPE_LIST}" | egrep -q 'WN|VOBOX' ); then
    if [ "$SITE_NAME" ]; then
echo "setenv SITE_NAME $SITE_NAME" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi
```



```
    if [ "$SCE_HOST" ]; then
echo "setenv SITE_GIIS_URL $SCE_HOST" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm/bin ]; then
    echo setenv PATH "\${PATH}:${INSTALL_ROOT}/d-cache/srm/bin:${INSTALL_ROOT}/d-cache/dcap/bin" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ -d ${INSTALL_ROOT}/d-cache/dcap/lib ]; then
    echo setenv LD_LIBRARY_PATH \${LD_LIBRARY_PATH}:${INSTALL_ROOT}/d-cache/dcap/lib >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ -d ${INSTALL_ROOT}/d-cache/srm ]; then
    echo setenv SRM_PATH ${INSTALL_ROOT}/d-cache/srm >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ "$$EDG_WL_SCRATCH" ]; then
    echo "setenv EDG_WL_SCRATCH $$EDG_WL_SCRATCH" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

for VO in `echo $VOS | tr '[:lower:]' '[:upper:]'`; do

    default_se=`eval echo '$$VO_${VO}_DEFAULT_SE`
    if [ "$default_se" ]; then
echo "setenv VO_${VO}_DEFAULT_SE $default_se" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi

    if ( ! echo "${NODE_TYPE_LIST}" | grep -q UI ); then
sw_dir=`eval echo '$$VO_${VO}_SW_DIR`
    if [ "$sw_dir" ]; then
        echo "setenv VO_${VO}_SW_DIR $sw_dir" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi
fi

done

if [ "$VOBOX_HOST" ]; then
    requires GSSKLOG
    if [ "${GSSKLOG}x" == "yesx" ]; then
        requires GSSKLOG_SERVER
        echo "setenv GSSKLOG_SERVER $GSSKLOG_SERVER" >> ${LCG_ENV_LOC}/lcgenenv.csh
    fi
fi

if [ "${DPM_HOST}" ]; then
    echo "setenv DPNS_HOST ${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.csh
    echo "setenv DPM_HOST ${DPM_HOST}" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi

if [ "$GLOBUS_TCP_PORT_RANGE" ]; then
    echo "setenv MYPROXY_TCP_PORT_RANGE \"\${GLOBUS_TCP_PORT_RANGE/ /,}\" >> ${LCG_ENV_LOC}/lcgenenv.csh
fi
```



```
fi

if ( echo $NODE_TYPE_LIST | egrep -q UI ); then
    cat << EOF >> ${LCG_ENV_LOC}/lcgenv.csh
if ( ! \${X509_USER_PROXY} ) then
    setenv X509_USER_PROXY /tmp/x509up_u\`id -u\`
endif
EOF
fi

echo endif >> ${LCG_ENV_LOC}/lcgenv.csh
##### csh #####

chmod a+rx ${LCG_ENV_LOC}/lcgenv.csh
chmod a+rx ${LCG_ENV_LOC}/lcgenv.sh

return 0
}
```

## 16.9. CONFIG\_JAVA

```
function config_java () {

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

# If JAVA_LOCATION is not set by the admin, take a guess
if [ -z "$JAVA_LOCATION" ]; then
    java=`rpm -qa | grep j2sdk-` || java=`rpm -qa | grep j2re`
    if [ "$java" ]; then
JAVA_LOCATION=`rpm -ql $java | egrep '/bin/java$' | sort | head -1 | sed 's#/bin/java##'`
    fi
fi

if [ ! "$JAVA_LOCATION" -o ! -d "$JAVA_LOCATION" ]; then
    echo "Please check your value for JAVA_LOCATION"
    return 1
fi

if ( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then

# We're configuring a relocatable distro

    if [ ! -d ${INSTALL_ROOT}/edg/etc/profile.d ]; then
mkdir -p ${INSTALL_ROOT}/edg/etc/profile.d/
    fi

    cat > $INSTALL_ROOT/edg/etc/profile.d/j2.sh <<EOF

JAVA_HOME=$JAVA_LOCATION
export JAVA_HOME
EOF
```



```
cat > $INSTALL_ROOT/edg/etc/profile.d/j2.csh <<EOF

setenv JAVA_HOME $JAVA_LOCATION
EOF

chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.sh
chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.csh

return 0

fi # end of relocatable stuff

# We're root and it's not a relocatable

if [ ! -d /etc/java ]; then
    mkdir /etc/java
fi

echo "export JAVA_HOME=$JAVA_LOCATION" > /etc/java/java.conf
echo "export JAVA_HOME=$JAVA_LOCATION" > /etc/java.conf
chmod +x /etc/java/java.conf

#This hack is here due to SL and the java profile rpms, Laurence Field

if [ ! -d ${INSTALL_ROOT}/edg/etc/profile.d ]; then
    mkdir -p ${INSTALL_ROOT}/edg/etc/profile.d/
fi

cat << EOF > $INSTALL_ROOT/edg/etc/profile.d/j2.sh
if [ -z "$PATH" ]; then
    export PATH=${JAVA_LOCATION}/bin
else
    export PATH=${JAVA_LOCATION}/bin:${PATH}
fi
EOF

chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.sh

cat << EOF > $INSTALL_ROOT/edg/etc/profile.d/j2.csh
if ( \${?PATH} ) then
    setenv PATH ${JAVA_LOCATION}/bin:\${PATH}
else
    setenv PATH ${JAVA_LOCATION}/bin
endif
EOF

chmod a+rx $INSTALL_ROOT/edg/etc/profile.d/j2.csh

return 0

}
```



## 16.10. CONFIG\_RGMA\_CLIENT

```
config_rgma_client(){
requires MON_HOST REG_HOST

INSTALL_ROOT=${INSTALL_ROOT:-/opt}

# NB java stuff now in config_java, which must be run before

export RGMA_HOME=${INSTALL_ROOT}/glite

# in order to use python from userdeps.tgz we need to source the env
if ( echo "${NODE_TYPE_LIST}" | grep TAR > /dev/null ); then
    . $INSTALL_ROOT/etc/profile.d/grid_env.sh
fi

${RGMA_HOME}/share/rgma/scripts/rgma-setup.py --secure=yes --server=${MON_HOST} --registry=${REG_HOST} --schema=${R

cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.sh
export RGMA_HOME=${INSTALL_ROOT}/glite
export APEL_HOME=${INSTALL_ROOT}/glite

echo \${PYTHONPATH} | grep -q ${INSTALL_ROOT}/glite/lib/python && isthere=1 || isthere=0
if [ \${isthere} = 0 ]; then
    if [ -z \${PYTHONPATH} ]; then
        export PYTHONPATH=${INSTALL_ROOT}/glite/lib/python
    else
        export PYTHONPATH=\${PYTHONPATH}:${INSTALL_ROOT}/glite/lib/python
    fi
fi

echo \${LD_LIBRARY_PATH} | grep -q ${INSTALL_ROOT}/glite/lib && isthere=1 || isthere=0
if [ \${isthere} = 0 ]; then
    if [ -z \${LD_LIBRARY_PATH} ]; then
        export LD_LIBRARY_PATH=${INSTALL_ROOT}/glite/lib
    else
        export LD_LIBRARY_PATH=\${LD_LIBRARY_PATH}:${INSTALL_ROOT}/glite/lib
    fi
fi
EOF

chmod a+rx ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.sh

cat << EOF > ${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.csh
setenv RGMA_HOME ${INSTALL_ROOT}/glite
setenv APEL_HOME ${INSTALL_ROOT}/glite

echo \${PYTHONPATH} | grep -q ${INSTALL_ROOT}/glite/lib/python && set isthere=1 || set isthere=0
if ( \${isthere} == 0 ) then
    if ( -z \${PYTHONPATH} ) then
        setenv PYTHONPATH ${INSTALL_ROOT}/glite/lib/python
    else
        setenv PYTHONPATH \${PYTHONPATH}\:${INSTALL_ROOT}/glite/lib/python
```



```
endif
endif

echo \${LD_LIBRARY_PATH} | grep -q \${INSTALL_ROOT}/glite/lib && set isthere=1 || set isthere=0
if ( \${isthere} == 0 ) then
  if ( -z \${LD_LIBRARY_PATH} ) then
    setenv LD_LIBRARY_PATH \${INSTALL_ROOT}/glite/lib
  else
    setenv LD_LIBRARY_PATH \${LD_LIBRARY_PATH}:\${INSTALL_ROOT}/glite/lib
  endif
endif
endif
EOF

chmod a+rx \${INSTALL_ROOT}/edg/etc/profile.d/edg-rgma-env.csh

return 0
}
```

## 16.11. CONFIG\_WORKLOAD\_MANAGER\_CLIENT

```
function config_workload_manager_client() {

INSTALL_ROOT=\${INSTALL_ROOT:-/opt}

if [ $SUID -eq 0 ]; then
  OUTPUT_STORAGE=\${OUTPUT_STORAGE:-/tmp/jobOutput}
else
  OUTPUT_STORAGE=\${OUTPUT_STORAGE:-\${HOME}/jobOutput}
fi

requires PX_HOST RB_HOST VOS

for i in $VOS ; do
if [ ! -d \${INSTALL_ROOT}/edg/etc/\$i ]; then
mkdir -p \${INSTALL_ROOT}/edg/etc/\$i
fi
if [ -f \${INSTALL_ROOT}/edg/etc/\$i/edg_wl_ui.conf ]; then
mv -f \${INSTALL_ROOT}/edg/etc/\$i/edg_wl_ui.conf /tmp/edg_wl_ui.conf.\$i.orig
fi
cat <<EOF >\${INSTALL_ROOT}/edg/etc/\$i/edg_wl_ui.conf
[
VirtualOrganisation = "\$i";
NSAddresses = "\$RB_HOST:7772";
LBAddresses = "\$RB_HOST:9000";
## HLR location is optional. Uncomment and fill correctly for
## enabling accounting
##HLRLocation = "fake HLR Location"
## MyProxyServer is optional. Uncomment and fill correctly for
## enabling proxy renewal. This field should be set equal to
## MYPROXY_SERVER environment variable
MyProxyServer = "\$PX_HOST"
]
}
```



```
EOF
done

if [ -f $INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf ]; then
mv -f $INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf /tmp/edg_wl_ui_cmd_var.conf.orig
fi
cat <<EOF >$INSTALL_ROOT/edg/etc/edg_wl_ui_cmd_var.conf
[
rank = - other.GlueCEStateEstimatedResponseTime;
requirements = other.GlueCEStateStatus == "Production";
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "${OUTPUT_STORAGE}";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "$RB_HOST:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
EOF

if [ -f $INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf ]; then
mv -f $INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf /tmp/edg_wl_ui_gui_var.conf.orig
fi
cat <<EOF >$INSTALL_ROOT/edg/etc/edg_wl_ui_gui_var.conf
[
JDLEDefaultSchema = "Glue";
Glue = [
rank = - other.GlueCEStateEstimatedResponseTime;
rankMPI = other.GlueCEStateFreeCPUs;
requirements = other.GlueCEStateStatus == "Production"
];
EDG = [
rank = - other.EstimatedTraversalTime;
rankMPI = other.FreeCPUs;
requirements = true
];
RetryCount = 3;
ErrorStorage = "/tmp";
OutputStorage = "${OUTPUT_STORAGE}";
ListenerPort = 44000;
ListenerStorage = "/tmp";
LoggingTimeout = 30;
LoggingSyncTimeout = 30;
LoggingDestination = "$RB_HOST:9002";
# Default NS logger level is set to 0 (null)
# max value is 6 (very ugly)
NSLoggerLevel = 0;
```



```
DefaultLogInfoLevel = 0;
DefaultStatusLevel = 0;
DefaultVo = "unspecified";
]
EOF

if [ ! -d $OUTPUT_STORAGE ]; then
mkdir $OUTPUT_STORAGE
fi

if [ $UID -eq 0 ]; then
chmod 1777 $OUTPUT_STORAGE
fi

if [ ! -d ${INSTALL_ROOT}/edg/var/etc/profile.d ]; then
mkdir -p ${INSTALL_ROOT}/edg/var/etc/profile.d
fi

for i in edg-wl-ui-env.csh edg-wl-ui-env.sh edg-wl-ui-gui-env.csh edg-wl-ui-gui-env.sh; do
if [ -f ${INSTALL_ROOT}/edg/etc/profile.d/${i} ]; then
cp -f ${INSTALL_ROOT}/edg/etc/profile.d/${i} ${INSTALL_ROOT}/edg/var/etc/profile.d
fi
done

}
```

## 16.12. CONFIG\_VOMSES

```
function config_vomses () {

requires VOS

if [ $UID -eq 0 ]; then
vomsespath="${INSTALL_ROOT}/edg/etc/vomses"
else
vomsespath="$HOME/.edg/vomses"
fi

if [ "$vomsespath" -a ! -d "$vomsespath" ]; then
mkdir -p $vomsespath
fi

for vo in $VOS; do
eval vomses='$VO_`echo $vo | tr '[:lower:]' '[:upper:]'`_VOMSES
if [ -z "$vomses" ]; then continue; fi
split_quoted_variable $vomses | while read line; do
server=`echo $line | awk '{print $2}'`
filename="${vo}-${server}"
echo $line | sed -e 's/ "/" "/g' -e 's/^"/' -e 's/$/"/' > $vomsespath/$filename
chmod 644 $vomsespath/$filename
done
done
```



```
if [ $UID -eq 0 ]; then
    if [ ! -d $INSTALL_ROOT/glite/etc/vomses ]; then
mkdir -p $INSTALL_ROOT/glite/etc/vomses
        fi
        cp -p $vomsespath/* $INSTALL_ROOT/glite/etc/vomses
    fi
return 0
}
```

### 16.13. CONFIG\_FTS\_CLIENT

```
function config_fts_client () {
INSTALL_ROOT=${INSTALL_ROOT:-/opt}

if [ -z "$FTS_SERVER_URL" ]; then
    return 0
fi

cat > ${INSTALL_ROOT}/glite/etc/services.xml <<EOF
<?xml version="1.0" encoding="UTF-8"?>

<services>

    <service name="EGEEfts">
        <parameters>
            <endpoint>${FTS_SERVER_URL}/services/FileTransfer</endpoint>
            <type>org.glite.FileTransfer</type>
            <version>3.0.0</version>
        </parameters>
    </service>

    <service name="EGEEchannel">
        <parameters>
            <endpoint>${FTS_SERVER_URL}/services/ChannelManagement</endpoint>
            <type>org.glite.ChannelManagement</type>
            <version>3.0.0</version>
        </parameters>
    </service>

</services>
EOF

return 0
}
```